


M15 Urinary System


Wednesday, April 24, 2013 4:09 PM

VoiceThread	
swf	http://justabitmoore.weebly.com/urinary-system.html
Captivate	









since it happens primarily in the glomerulus which is housed inside of the Bowman's capsule.

The Bowman Capsule is made up of a parietal layer of simple squamous epithelium. It opens into the proximal convoluted tubule.

The glomerulus receives the blood by the afferent arteriole. Embedded in the arteriole wall are granular cells. Another name for these cells is juxtaglomerular cells.

There are holes in the glomerular capillaries. The holes are called fenestrae (fen es tray) and they make these capillaries more porous than other capillaries in the body.

The glomerulus is a visceral layer composed of podocytes which are specialized cells that actually attach to the glomerular capillaries by means of small processes called foot processes.

The purpose of the design is to allow everything but the blood cells and proteins leave the blood vessel. The liquid that has left the blood supply here is called filtrate and it is essentially the same as interstitial fluid in composition.

✓ Notice that the afferent arteriole is considerably larger that the efferent arteriole. There are two reasons for that, one is that the blood supply leaving the glomerulus will have part of the volume removed due to filtering, but the purpose is also to keep the pressure in the glomerulus high enough that the filtrate can leave the glomerulus efficiently.

Average adult have 5 liters of blood and the volume passes through the heart every minute. The blood flow to the kidneys is about 20% of that


The renal blood flow rate coming through the glomerulus is about 1 liter of blood per minute which is about 1/5 of the total blood supply in your body.


The amount of pressure inside the glomerulus is 55 mm Hg. There are counter-pressures too. Water tries to go back in to the glomerulus because of osmosis. This is colloid osmotic pressure and it amounts to about 30 mm Hg.

There is also capsular pressure that comes from the walls of the Bowman Capsule resisting over-filling by the filtrate. It runs about 15 mm Hg.

Overall then, the outward pressure sending the filtrate down the proximal tube is 10 mm Hg.

If the pressures get our of balance then renal shutdown is a very real possibility because the blood cannot be cleansed. Some possible causes of the pressure drop are hemorrhage or severe dehydration.






nephron, they pass close to the network of peritubular capillaries. These capillaries are what the nephron is trying to get the good stuff back to.


Let's continue our filtrate's journey from the Bowman's capsule and glomerulous which together are called the renal corpuscle.

The walls of the nephron tubules are very thin. The one nearest the Bowman capsule is the proximal tubule . It is made up of simple cuboidal epithelium because there must be room for cellular machinery to facilitate reabsorption. The cells have a brush border to increase surface area much like the intestines have villi. This increases the rate of reabsorption.

Most of the reabsorption happens in the proximal tubule: 65% of the waterand virtually 100% of the glucose will be able to be returned to the peritubular capillaries from this structure.

The loops of Henle is made up of simple squamous cells. It leads to the distal tubule and the collecting ducts. When the filtrate enters the collecting tube then it is officially urine.





The materials that must be actively absorbed are nutrients, minerals amino acids, and glucose. These will not normally pass through the membranes of the nephron. To move these materials back into the blood supply, energy in the form of ATP must me expended and carriers must be used.

Tubular Maximus (T-max) is the maximum rate of reabsorption by active transport through the nephron tubules. This limit occurs because there are a finite number of carriers taking the materials out of the filtrate. The carrier quantity is calibrated to what the body needs. If you need a lot of a substance, more carriers will be there to perform the job of getting the substance back in to the blood supply. If you need only a little, then only a few carriers for that substance will be provided. You hit the T-max when all the carriers are busy and some of the material then passes on to become urine without being reabsorbed.

Sodium is usually in urine since we take in so much of it that we are usually at T-max. If glucose levels are too high, you will spill glucose into urine because it is at T-

The glomerulus isn't supposed to let proteins get through, but If any proteins did slip through the filtration step, they will be returned to the blood supply through pinocytosis.

Nest, let's look at passive absorption ...

Substances that are passively absorbed move freely through the membranes because of differences in concentration.

The proximal tubule will have internal and external concentrations that are about equal.


The descending limb if the loop of Henle will have filtrate that is of higher concentration than the fluids of the blood plasma.

The ascending loop will have much of the filtrate's substances removed, so the blood plasma now will have a higher concentration.

The distal tubule will also be an area where the blood plasma will be more concentrated than the filtrate.

Some of the substances that will passively absorbed are water, urea, and Chlorine ions.

🖌 Step 3 - Secretion



Some chemicals that have passed back in to the blood we don't want there. They must be secreted back into the nephron.

The desk drawer analogy helps us understand this. After adding things back in to the desk drawer you may decide you don't want something after all and put it back in the junk pile to be thrown away. You secrete it back to the junk pile.

Step 4 is the reabsorption of water.


Step 4 is water Reabsorption. Some sections of the nephron are permeable and others impermeable to water. These variations of permeability are essential to the control of water levels that return to the blood.

In the distal tubule and the descending loop of Henle, the membranes are permeable to water. The interstitial fluid in the kidneys here reach up to 4x more concentrated than in the rest of the body as you move toward the tip of the loop. This efficiently pulls water out of the tubule and loop and in to the medulla. The vasa recta capillary in the medulla then reabsorbs it.

Ascending limb of the loop of Henle is impermeable to water. Its job is to actively moves electrolytes back in to the blood flow.

The distal tubule and collecting duct vary their permeability based on ADH levels. ADH is produced in the hypothalmus in response to cell shrinkage. If the cells shrink it is because the concentration in the blood plasma is too high so the water in the cells moves out toward the higher concentration. This cell shrinkage can damage the cell. It will be important to get more water into the plasma to reduce concentration there. The reverse can be the case as well and the lack of ADH will slow the amount of water that continues to be absorbed in the distal tubule and collecting duct.

Transitional Squamous epithelium line the bladder = stretch without tearing. Size of thumb when empty.




Notice that there are two sphincters. One is involuntary and the other voluntary.

Babies - automatic system When we are babies, a full bladder results in an impulse to spinal column which then signals the internal sphincter to relax and allow urine to flow.

Myleination of the nervous system so the spinal column can send a signal to the cerbral cortex will begin giving us control of the voluntary valve called the external urinary sphincter. Before the myleination, it opens with the other sphincter automatically.

As we age we lose our nervous system control and the system reverts back to like it is when we are a baby. This is called incontinence.



When we listed the 7 functions of the urinary system, number 4 was blood pressure control. This is because the kidneys can regulate how much water is in the blood. The more water there is the higher the blood pressure. You cannot just add water to the blood supply though. If concentration doesn't stay balances in the plasma diffusion and osmosis will get messed up, so with the water, you must also increase the solutes in the blood along with it.

The afferent arteriole has juxtaglomerular cell also called granular cells. These detect the blood sodium levels and blood pressure.

Drop in either they release renin. Renin is an enzyme that will activate angiotensinogen in the liver. (-ogen means precursor, -angio means blood vessel, -tensin meand pressure)

When the above two interact a peptide called angiotensin I is produced

Angiotensin II -

- 1. Increases vasoconstriction powerfully
- 2. Makes you thirsty
- 3. Makes you want salt
- 4. Released aldosterone which increases sodium reabsorption

More salt will cause more water to be retained and increases pressure.

When volume is high, it stretches the atria which triggers natriuretic hormone release. This hormone inhibits the nephrons from re-absorbing sodium which lowers water levels bringing blood pressure down.

The last function we will discuss is pH control. Normal pH ranges from 7.35 to 7.45. That is a pretty narrow range to have to keep things in.

